

# How to Set Up R Kernel in Jupyter Lab

---

NAS currently supports three versions of the R machine learning platform:

- R Versions 3.6 and 4.2 are provided in the r3\_6 and r4\_2 NAS conda environments, respectively.
- R Version 4.1 is provided as a NAS software package.

The versions in conda come preinstalled with many of the popular R packages used in data science and machine learning, including Jupyter Lab. Although the version provided as a NAS software package does not include Jupyter Lab, you can configure Jupyter Lab to work with this version of R by following the instructions below.

Before You Begin: Complete all the steps in the following articles:

- [Secure Setup for Using Jupyter Notebook for Machine Learning Development on NAS Systems](#)
- [Using Jupyter Notebook for Machine Learning Development on NAS Systems](#)

Complete the following steps to install R and set up Jupyter Lab to use it:

1. Load the following NetBSD Packages Collection (pkgsr) module and start R:

```
pfe27% module load pkgsr/2022Q1-rome
pfe27% R
```

2. Install IRkernel in R:

```
> install.packages("IRkernel")
```

3. Run IRkernel in R:

```
> IRkernel::installspec()
```

4. Copy the IRkernel directory to your Jupyter data directory. For example, if your IRkernel directory is in \$HOME/R/x86\_64-redhat-linux-gnu-library/4.1, do:

```
> cp -R $HOME/R/x86_64-redhat-linux-gnu-library/4.1/IRkernel $HOME/.local/share/jupyter
```

5. Change the R path (the first "R") in the \$HOME/.local/share/jupyter/IRkernel/kernelspec/kernel.json file to:  
/nasa/pkgsr/toss4/2022Q1-rome/bin/R (or other R)

6. Load Jupyter and run R.

---

Article ID: 685

Last updated: 24 Jul, 2023

Updated by: Moyer M.

Revision: 15

Machine Learning -> Machine Learning at NAS -> How to Set Up R Kernel in Jupyter Lab

<https://www.nas.nasa.gov/hecc/support/kb/entry/685/>